

Setup ssh-key exchange

It is possible to automatically login in a ssh session on a remote system. To make this possible ssh keys needs to be exchanges between the client and target. For more information see also: http://backuppc.sourceforge.net/faq/ssh.html#why_do_i_need_ssh. You can do this for any user on the target system. The example below assumes logging in as root user on the target system.

Key Generation

On the Target System

As root on the target machine, use ssh-keygen to generate a public/private key pair:

```
# cd /root/.ssh
# ssh-keygen -t rsa -b 2048
-----
# Generating public/private rsa key pair.
Enter file in which to save the key (/root/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /root/.ssh/id_rsa.
Your public key has been saved in /root/.ssh/id_rsa.pub.
```

As a password, you would type nothing (just enter). This will save the public key in /root/.ssh/id_rsa.pub and the private key in /root/.ssh/id_rsa, if you don't specify another location.

On the Client System

This might not be necessary if the client key has already be created for other targets, so you can reuse it. Repeat the above steps for the user 'oscar' on the client that will execute the ssh. Login as user on the client and perform the following steps:

```
$ cd /home/oscar/.ssh
$ ssh-keygen -t rsa -b 2048
-----
# Generating public/private rsa key pair.
Enter file in which to save the key (/home/oscar/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /home/oscar/.ssh/id_rsa.
Your public key has been saved in /home/oscar/.ssh/id_rsa.pub.
```

After this the file ~/.ssh/id_rsa.pub should exist in the .ssh in the home directory of user 'oscar'. Make a copy of the public key to make it recognizable.

Key Exchange

To allow the client to ssh to the target system as root, you need to place the client's public key into root's authorized list on the target system. There are 2 different ways to achieve this:

- Manual
- With 'ssh-copy-id'

Key transfer - Manual

Append client's public key (BackupPC_id_rsa.pub) to root's /root/.ssh/authorized_keys2 file on the client:

On the Target System

Get the public key from the client system and add it to the 'authorized keys':

```
# cd /root/.ssh
# scp oscar@192.168.xx.xx:/home/oscar/.ssh/id_rsa.pub client_id_rsa.pub
# touch ~/.ssh/authorized_keys2
# cat client_id_rsa.pub >> ~/.ssh/authorized_keys2
# rm client_id_rsa.pub
```

On the Client System

You need to place the target's public key into client's ~/.ssh/known_hosts file, otherwise you will get a "Host key verification failed." error, and the client will not be able to log into the target system. To place the target public key into the ~/.ssh/known_hosts file, you need to do this (make sure ~/.ssh/target_id_rsa.pub is the client's public key, which needs to be copied from the target system):

```
$ scp root@192.168.xx.xx:/root/.ssh/id_rsa.pub target-key.pub
$ touch ~/.ssh/known_hosts
$ cat ~/.ssh/target-key.pub >> ~/.ssh/known_hosts
$ rm target-key.pub
```

Or simply try to ssh from client to target as root. The key will be placed automatically in known_hosts file.

Key transfer - with ssh-copy-id

Copy your keys to the target system:

```
$ ssh-copy-id remoteusername@targetsistem
```

```
remoteusername@targetsystem's password:
```

Now try logging into the machine, with ssh 'remoteusername@targetsystem'. The key of your system should now be placed in the .ssh subdirectory in the home directory of remoteusername on the target system.

```
/home/remoteusername/.ssh/authorized_keys
```

or

```
/root/.ssh/authorized_keys
```

or on openwrt:

```
/etc/dropbear/authorized_keys
```

Test

This should now work from the server to the client:

```
$ ssh root@192.168.xx.xx
```

If everything went ok, you should be logged in directly without a password prompt.

From:

<https://wiki.oscardegroot.nl/> - **HomeWiki**

Permanent link:

<https://wiki.oscardegroot.nl/doku.php?id=linux:debian:ssh-key-transfer&rev=1622130489>

Last update: **2022/01/15 11:38**

