Bluetooth

```
bluetoothctl
```

List options:

```
bluetoothctl help
------------------
advertise                                    Advertise Options Submenu
monitor                                      Advertisement Monitor
Options Submenu
scan                                         Scan Options Submenu
gatt                                         Generic Attribute Submenu
admin                                        Admin Policy Submenu
player                                       Media Player Submenu
endpoint                                     Media Endpoint Submenu
transport                                    Media Transport Submenu
list                                         List available controllers
show [ctrl]                                  Controller information
select <ctrl>                                Select default controller
devices [Paired/Bonded/Trusted/Connected]    List available devices,
with an optional property as the filter
system-alias <name>                          Set controller alias
reset-alias                                  Reset controller alias
power <on/off>                               Set controller power
pairable <on/off>                            Set controller pairable
mode
discoverable <on/off>                        Set controller
discoverable mode
discoverable-timeout [value]                 Set discoverable timeout
agent <on/off/capability>                    Enable/disable agent with
given capability
default-agent                                Set agent as the default
one
advertise <on/off/type>                      Enable/disable advertising
with given type
set-alias <alias>                            Set device alias
scan <on/off/bredr/le>                       Scan for devices
info [dev]                                   Device information
pair [dev]                                   Pair with device
cancel-pairing [dev]                         Cancel pairing with device
trust [dev]                                  Trust device
untrust [dev]                                Untrust device
block [dev]                                  Block device
unblock [dev]                                Unblock device
remove <dev>                                 Remove device
connect <dev>                                Connect device
disconnect [dev]                             Disconnect device
menu <name>                                  Select submenu
```

```
version                                       Display version
quit                                          Quit program
exit                                          Quit program
help                                          Display help about this
program
export                                        Print environment
variables
```

```
[LOXJIE BT5.0B]# devices
Device 20:FA:BB:03:67:FC Gato Audio DIA-250S
Device 00:13:5B:00:FB:E4 LOXJIE BT5.0B
```

```
[LOXJIE BT5.0B]# info 00:13:5B:00:FB:E4
Device 00:13:5B:00:FB:E4 (public)
    Name: LOXJIE BT5.0B
    Alias: LOXJIE BT5.0B
    Class: 0x00240414
    Icon: audio-card
    Paired: yes
    Bonded: yes
    Trusted: yes
    Blocked: no
    Connected: yes
    LegacyPairing: no
    UUID: Serial Port            (00001101-0000-1000-8000-00805f9b34fb)
    UUID: Audio Sink             (0000110b-0000-1000-8000-00805f9b34fb)
    UUID: A/V Remote Control Target (0000110c-0000-1000-8000-00805f9b34fb)
    UUID: Advanced Audio Distribu.. (0000110d-0000-1000-8000-00805f9b34fb)
    UUID: A/V Remote Control      (0000110e-0000-1000-8000-00805f9b34fb)
    UUID: PnP Information         (00001200-0000-1000-8000-00805f9b34fb)
    UUID: Generic Access Profile  (00001800-0000-1000-8000-00805f9b34fb)
    UUID: Battery Service         (0000180f-0000-1000-8000-00805f9b34fb)
    Modalias: bluetooth:v000ApFFFFdFFFF
```